USB-Treiber Installation:

🖉 USB to UART Bridge VCP D	rivers - Windows Internet Explorer	\mathbf{X}
🔄 🗢 🖻 https://www.sila	abs.com/products/mcu/Pages/USBto 💌 🔒 🚱 🗙 🚼 Google 🖉	
<u>D</u> atei <u>B</u> earbeiten <u>A</u> nsicht <u>F</u> av	voriten Extras ?	
× Google	Suche 🕶 Mehr » 🥥 Anmelden 🍕	6-
🚖 Favoriten 🛛 👍 🕖 Vorgeschla	agene Sites 🔻 📶 Kostenlose Hotmail 🙋 Web Slice-Katalog 👻	
🕶 USB to UART Bridge VCP Drivers	🚵 🔹 🔊 🕐 🖃 🌧 🔹 Sejte 🗸 Sigherheit 🗸 Extras 🗸 🔞 🗸	»
Diese Website möchte das folgend die Ausführung zulassen möchten	de Add-On ausführen: "name.dll" von "Microsoft Corporation". Klicken Sie hier, wenn Sie der Website vertrauen und	×
		^
	Home About Us News Inves	stx
+ Products + Applicat	tions + Support + Buy or Sample	-
Silicon Labs > Products > MCUs >	USB to UART Bridge VCP Drivers	
MCUs		
	CP210X USB to UAR I Bridge VCP Drivers	F
Overview	operation as a Virtual COM Prote to facilitate host communication with CP210x products.	
MCU Parametric	These devices can also interface to a nost using the USBApress direct access driver.	
Search	Download for Windows XP/Server 2003/Vista/7 (v6.3a)	P I
Analog Intensive MCUs	The CP210x Manufacturing DLL and Runtime DLL have been updated and must be used with v6.0 and later of the CP210x Windows VCP Driver. Application Note Software	
Automotive & Industrial MCUs	downloads affected are AN144SW.zip, AN205SW.zip and AN223SW.zip. If you are using a 5.x driver and need support you can download archived Application Note Software.	
Capacitive Touch Sense MCUs	<u>VCP Driver Kit</u>	
Low-Power MCUs	Kevision History Lise Driver Installation Litility Application Note AN225	
<		
🕖 https://www.silabs.com/Support%	620Documents/Sc 😜 Internet 🎻 🗣 100% 🔻	•

USB-Treiber VCP-Driver Kit herunterladen

Dateidownload - Sicherheitswarnung
Möchten Sie diese Datei speichern oder ausführen?
Name: CP210x_VCP_Win_XP_S2K3_Vista_7.exe
Typ: Anwendung, 6,79 MB
Von: www.silabs.com
A <u>u</u> sführen <u>S</u> peichern Abbrechen
Dateien aus dem Internet können nützlich sein, aber dieser Dateityp kann eventuell auf dem Computer Schaden anrichten. Führen Sie diese Software nicht aus und speichern Sie sie nicht, falls Sie der Quelle nicht vertrauen. <u>Welches Risiko besteht?</u>

Download Speichern:

Speichern unte	er					? 🛛
Spejchern in:	🗁 Drivers	~	0	3 🖻	•	
Zuletzt verwendete D						
Desktop						
Eigene Dateien						
Arbeitsplatz						
S	Datei <u>n</u> ame:	CP210x_VCP_Win_XP_S2K3_Vista	_7.exe	*		<u>S</u> peichern
Netzwerkumgeb	Datei <u>t</u> yp:	Anwendung		*		Abbrechen



Doppelklicken Sie auf den Treiber.

Datei öf	fnen - Sicherheitswarnung	×
Der He diese S	erausgeber konnte nicht verifiziert werden. Möchten Sie Software ausführen?	
	Name: CP210x_VCP_Win_XP_52K3_Vista_7.exe	
	Herausgeber: Unbekannter Herausgeber	
	Typ: Anwendung	
	Von: C:\Drivers	
	Ausführen Abbrechen	
Vor 🗸	dem Öff <u>n</u> en dieser Datei immer bestätigen	
8	Diese Datei verfügt über keine gültige digitale Signatur, die den Herausgeber verifiziert. Sie sollten nur Software ausführen, die von Herausgebern stammt, denen Sie vertrauen. <u>Welche Software kann</u> ausgeführt werden?	n

Klicken sie auf Ausführen:

Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Se 🗔 🗖 🔀
Existing Installed Instances Detected Select the appropriate application instance to maintain or update.
Setup has detected one or more instances of this application already installed on your system. You can maintain or update an existing instance or install a completely new instance. Install a new instance of this application. Maintain or update the instance of this application selected below:
Display Name Install I Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Server/Vista/7 c:\SiLa
InstallShield

Klicken Sie auf Next.

Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Server/Vi 🔀		
	Welcome to the InstallShield Wizard for Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Server/Vista/7 v6.3a The InstallShield Wizard will copy Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Server/Vista/7 v6.3a onto your computer. To continue, click Next.	
	< <u>B</u> ack <u>N</u> ext > Cancel	

Klicken Sie auf Next.

Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Server/Vi 🔀
License Agreement Please read the following license agreement carefully.
END-USER LICENSE AGREEMENT IMPORTANT: READ CAREFULLY BEFORE AGREEING TO TERMS
SILICON LABORATORIES INC., SILICON LABORATORIES INTERNATIONAL PTE. LTD., AND THEIR AFFILIATES (COLLECTIVELY, "SILICON LABS") HAVE DEVELOPED CERTAIN MATERIALS (E.G., DEVELOPMENT TOOLS, EXAMPLE CODE, EMBEDDABLE CODE, DLLs, SOFTWARE/COMPUTER PROGRAMS AND OTHER THIRD PARTY PROPRIETARY MATERIAL) ("LICENSED MATERIALS") THAT YOU MAY USE IN CONJUNCTION WITH SILICON LABS' MCU PRODUCTS. ANY USE OF THE LICENSED MATERIALS IS SUBJECT TO THIS END-USER LICENSE
accept the terms of the license agreement
O I do not accept the terms of the license agreement
InstallShield
< <u>B</u> ack <u>N</u> ext > Cancel

Akzeptieren Sie die Lizenzbedingungen und klicken Sie auf Next.

Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Server/Vi 🔀
Choose Destination Location Select folder where setup will install files.
Setup will install Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Server/Vista/7 v6.3a in the following folder.
To install to this folder, click Next. To install to a different folder, click Browse and select another folder.
Destination Folder
c:\\CP210x\Windows_XP_S2K3_Vista_7_2_3
InstallShield
< <u>B</u> ack <u>N</u> ext > Cancel

Wählen Sie das Verzeichnis und klicken Sie auf Next.

Silicon Laboratories CP210x VCP Drivers for Windows XP/2003 Server/Vi 🗙
Ready to Install the Program The wizard is ready to begin installation.
Click Install to begin the installation.
If you want to review or change any of your installation settings, click Back. Click Cancel to exit the wizard.
InstallShield <u>< B</u> ack <u>Install</u> Cancel

Klicken Sie auf Install.



Launch the CP210x VCP Driver Installer muss angeklickt sein. Launch the CP210x driver. Klicken Sie auf Finish.

🚜 Silicon Laboratories CP210x USB to UART Brid	dge Driver Installer 🔀		
Silicon Laboratories Silicon Laboratories CP210x USB to UART Bridge			
Installation Location:	Driver Version 6.3		
C:\Programme\Silabs\MCU\CP210x\			
Change Install Location Install Cancel			
Click Install:			
Update			
Are you sure you want to update version 6.1 to v	ersion 6.3?		
la <u>N</u> ein			

Falls Sie bereits eine ältere Version installiert haben, dann klicken Sie auf Ja.

Yes, if you have an older version on the PC. Ja, falls ältere Version auf dem PC.

Geänderte Systemeinstellungen	
?	Die Änderungen werden erst nach dem Neustart des Computers wirksam.
-V	Soll der Computer jetzt neu gestartet werden?
	la <u>N</u> ein

Klicken Sie auf Ja, um die Installation abzuschließen.

Nach dem vollständigen Neustart des Rechners die USB-Schnittstelle #7168.6 an eine USB-Schnittstelle anstecken.

Nach einiger Zeit kommt die Meldung neue Hardware gefunden.

Schauen Sie im Gerätemanager, wo sich der COM-Port installiert hat.

After the complete restart of the PC, plug in the USB-adapter #7168.6 to an USB-Port. After some time, new hardware found is displayed.

After this check the COM-Port number at the hardware manager.

